

Table des matières

Changer marge de bruit	3
Changer mode ADSL	3
Voir/éditer paramètres	3
tplink	3
tplink2	3

Changer marge de bruit**ADSL2**

```
wan dmt2 set snroffset 1280 1280
```

ADSL1

```
wan dmt set snroffset 1280
```

Changer mode ADSL

```
wan adsl opencmd gdmnt  
wan adsl opencmd adsl2  
wan adsl opencmd adsl2plus
```

Voir/éditer paramètres

```
sys view autoexec.net  
sys edit autoexec.net
```

```
wan dmt show dmt  
wan dmt2 show dmt
```

tplink

```
sys dhcpprobe no  
ip nogateway 1  
ip rip merge on  
ip nat loopback on  
ip rip activate  
ip icmp discovery enif0 off  
ppp ipcp compress off  
sys wdog sw on  
sys quick enable  
wan adsl rate off  
ether driver etherppp on  
wan dmt2 set pmonoff off  
sys cwmp setnovaluetype 1  
sys cwmp recvtimeout 30  
w dmt2 set largeD 2  
w dmt2 set lpr off  
w dmt eoc dyingasp off  
w ghs set multi 3 3  
wan adsl opencmd gdmnt  
wan dmt set snroffset -1600
```

ADSL2 : 4096

tplink2

```
sys dhcpprobe no  
ip nogateway 1  
ip rip merge on  
ip nat loopback on  
ip rip activate  
ip icmp discovery enif0 off  
ppp ipcp compress off  
sys wdog sw on  
sys quick enable  
wan adsl rate off  
ether driver etherppp on  
wan dmt2 set pmonoff off  
sys cwmp setnovaluetype 1  
sys cwmp recvtimeout 30  
w dmt2 set largeD 2  
w dmt2 set lpr off
```

```
w dmt eoc dyingasp off
w ghs set multi 3 3
wan adsl opencmd gdm
wan dmt set snrmoffset -768
```

ADSL2 : 2128

From:
<https://unix-bck.ndlp.info/> - **Where there is a shell, there is a way**

Permanent link:
<https://unix-bck.ndlp.info/doku.php/informatique:reseau:xdsl:xdsl>

Last update: **2017/10/27 14:21**